

FAQ: Where Can I Find My Atalasoftware License Files

Atalasoftware licensing is file-based (there are certain code based licenses which I will address below - but they're uncommon), and we often get asked where does one find the files.

SDK Licenses (for developers and certain automated build machines)

SDK (development / testing / build) licenses are activated per developer using our activation wizard. For more on activation, please see:

[HOWTO: Activate DotImage SDK or Server \(Including Offline Activation\)](#)

That activation process will put the license file(s) in a specific location that is unique to the user who activates and also to the major.minor version of DotImage

The short answer is the file goes into

C:\Users**YOUR_USERNAME**\AppData\Local\Atalasoftware\DotImage **X.Y**/

the files will have names ending in .lic such as

- Atalasoftware.dotImage.lic
- Atalasoftware.dotImage.Pdfium.lic
- Atalasoftware.dotImage.Office.lic
- Atalasoftware.WingScan.lic
- etc...

The license file is uniquely bound to the machine where it was activated on and can not be copied /moved to another machine. If you're changing machines, you need to activate on the new machine. Please see the above mentioned KB article link for how to activate and feel free to [create a support case with Atalasoftware support](#) if you have questions/issues activating your license.

YOUR_USERNAME

The username in **YOUR_USERNAME** is your windows username, not the user name (email address) you use to activate the license. If your name is "John Doe", your windows login

FAQ:Where Can I Find My Atalasoftware License Files

may be John.Doe or JDoe or John etc... so you'll need to

DotImage X.Y

The **X.Y** part of the folder name is the MAJOR.MINOR version - so you may be using 11.4.0.3.0.311 but your license will be activated for 11.4 - similar for older versions - we separate licenses only on those major/minor releases so that folder may be "DotImage 11.4" or "DotImage 11.3" or "DotImage 10.7" etc...

Putting it Together

So for John Doe who logs into windows as JDoe and activated both 10.7 and 11.4, he will have 2 directories containing his Atalasoftware licenses

For his 10.7 version, they will be in

C:\users\JDoe\AppData\Local\Atalasoftware\DotImage 10.7\

and for his 11.4, they will be in

C:\users\JDoe\AppData\Local\Atalasoftware\DotImage 11.4\

Automated Build Processes

Each developer using DotImage requires their own serials / licenses. An Automated Build process requires licensing as if it were a separate developer

The license should be activated while logged on to the machine AS the build user. Given the example above where John Doe (logging on to his machine as JDoe) is also managing an automated build machine - on that machine the build logs in as "TFS_Build" when he activates that he would log onto the machine as TFS_Build and activate as normal - so in that case the licenses will be found in

For the 10.7 version, they will be in

C:\users\TFS_Build\AppData\Local\Atalasoftware\DotImage 10.7\

FAQ:Where Can I Find My Atalasoft License Files

and for 11.4, they will be in

C:\users\TFS_Build\AppData\Local\Atalasoft\DotImage 11.4\

Server Licensing

Identifying Server Licenses

Server licenses are distinct from SDK (dev/build) licenses and can be identified by the X in the first group of letters.

Example:

DotImage Document Imaging - our base SDK and the basis for most all projects using DotImage - serials start with DID2 for developer/SDK licenses but DIDX2 for server versions.

PdfReader addon serials changed over time - for 10.7 and older they were PRS2 for SDK licenses and PRSX2 for server but for 11.0 and newer, they are PRP2 and PRPX2 respectively.

Over time we've had a LOT of different serials for different products please see [INFO: Descriptions of Various Licenses](#) for a complete list.

Locating Server Licenses

Unlike SDK licenses, when activated, server licenses are not automatically placed in any specific location. Instead, the activation wizard will ask you where you want to save the license.

As a general rule, for a server deployment, the license file is placed in the application bin directory next to the Atalasoft.*.dll files being referenced/included in the deployment.

NOTE that one serial / license file for a given version of an Atalasoft product is good for any

FAQ:Where Can I Find My Atalasoftware License Files

and all apps on the server so EACH APP may have its own copy of the Atalasoftware licenses it needs - this is acceptable - to activate once for the server then copy the same license file to many different apps as long as they are all on the same server.

So to locate a license for a given application, start by looking in the app's bin directory next to the Atalasoftware.dotImage.dll and other Atalasoftware.*.dll files being referenced. There may be many different files (Atalasoftware.dotImage.lic, Atalasoftware.dotImage.Pdfium.lic, Atalasoftware.PdfDoc.lic etc...)

Alternate Locations and Special Cases

Program Files (x86)

Support does not recommend using this location, but at times it's useful - so it's worth checking to even see if it exists

C:\Program Files (x86)\Atalasoftware\DotImage X.Y\bin

again, the X.Y being 11.4, 11.3, 11.2, etc...

This is a left over relic from over 15 years ago when it used to be the default to install licenses to the SDK install directory. We stopped doing that years ago, switching to the local user AppData\Local directory to avoid needing to be running as Administrator to make changes / activate licenses.

Custom License File location

There is a way to specify a custom location for licenses by setting a String key called AssemblyBasePath. The process for doing so is laid out in:

[HOWTO: Configure your deployment to use Atalasoftware license files in a custom location](#)

If you are unable to find your licenses, they may have been set in that path (it may also be set to the above Program Files location as a default

FAQ:Where Can I Find My Atalasoft License Files

Use your Registry editor to find that key (if present)

Code Based Licenses

In rare cases, you may have a CCW, PKL or ATL license which is an XML string that is embedded directly in code with a call to

```
Atalasoft.Licensing.SetAssemblyLicense("string of xml here");
```

If you're unable to find your license files you can search your code for "SetAssemblyLicense" to see if you're using such a license in your app.

Search for Atalasoft.*.lic

You can always search your entire driver for Atalasoft.*.lic files

Atalasoft Knowledge Base

<https://www.atalasoft.com/kb2/KB/50417/FAQWhere-Can-I-Find-My-Atalasoft-Lic...>